

SLMgr - Commandes et Options pour Windows Product Key / KMS / Token / AD Activation

Syntaxe de SLMgr :

1

Options of SLMgr

slmgr /dli (display the current license information of Windows with activation status and last 5 characters of partial product key)

[slmgr -dli](#)

slmgr /dlv (stands for display license information, verbose, similar to -dli switch but with more detailed information)

[slmgr -dlv](#)

slmgr /ipk <xxxxx-xxxxx-xxxxx-xxxxx-xxxxx> (enter a new or [replace and change the current product key](#) with the new product key supplied at xxxxx-xxxxx-xxxxx-xxxxx-xxxxx)

slmgr /xpr (shows expiration date of current license state if Windows Vista is not permanently activated)

[slmgr -xpr](#)

slmgr /ato (activate Windows Vista license and product key against Microsoft's server)

slmgr /upk (uninstall current installed product key and return license status back to trial state)

slmgr /cpky (clear the product key from the registry to prevent disclosure attacks)

slmgr /ilc <license file> (install license)

slmgr /rilc (re-install system license files)

slmgr /rearm (reset the licensing status and activation state of the machine)

slmgr /rearm-app (reset the licensing status of the given app)

slmgr /rearm-sku (reset the licensing status of the given SKU)

The following options used with offline activation such as through phone:

```
slmgr /dti (display installation ID for offline activation)
```

```
slmgr /atp <confirmation ID> (activate product with user-provided Confirmation ID)
```

SLMgr options for Volume Licensing Activation Using KMS (Key Management Service):

```
slmgr /skms activationservername
```

```
slmgr /sprt <port>
```

```
slmgr /skms activationservername:port (set the KMS server and the port used for KMS activation for Windows Vista Business edition and Windows Vista Enterprise edition)
```

For example:

```
1
```

Or:

```
slmgr /skms 192.168.1.1:6888
```

```
1
```

```
slmgr /ckms (clear the name of KMS server used to default and port to default)
```

```
slmgr /skms-domain <FQDN> (set the specific DNS domain in which all KMS SRV records can be found)
```

```
slmgr /ckms-domain (clear the specific DNS domain in which all KMS SRV records can be found)
```

```
slmgr /skhc (enable KMS host caching)
```

```
slmgr /ckhc (disable KMS host caching)
```

```
slmgr /sai <activation interval> (sets the interval in minutes for unactivated clients to attempt KMS connection.)
```

```
slmgr /sri <activation interval> (sets the renewal interval in minutes for activated clients to attempt KMS connection)
```

```
slmgr /sdns (enable DNS publishing by the KMS host)
```

```
slmgr /cdns (disable DNS publishing by the KMS host)
```

```
slmgr /spri (set the KMS priority to normal)
```

```
slmgr /cpri (set the KMS priority to low)
```

```
slmgr /act-type (set a value in the registry that limits volume activation to a single type: 1 for Active Directory; 2 for KMS activation; 3 for token-based activation; 0 for any activation type)
```

SLMgr Options for Token-based Volume Activation:

```
slmgr /lil (list installed Token-based Activation Issuance Licenses)
```

```
slmgr /ril <ILID> <ILvID> (remove installed Token-based Activation Issuance Licenses)
```

```
slmgr /lrc (list Token-based Activation Certificates)
```

```
slmgr /fta <Certificate Thumbprint> <PIN> (force Token-based activation)
```

SLMgr Options for Active Directory-based Activation:

```
slmgr /ad-activation-online <Product Key> (collect Active Directory data and initiates Active Directory forest activation using the credentials that the command prompt is running)
```

```
slmgr /ad-activation-get-IID <Product Key> (start Active Directory forest activation in phone mode)
```

```
slmgr /ad-activation-apply-cid <Product Key> <Confirmation ID> (complete activation through activation phone call)
```

```
slmgr /ao-list (display all of the activation objects that are available to the local computer)
```

```
slmgr /del-ao <AO_DN> (delete the specified activation object from the forest)
```

Note: If when you enter slmgr command and an error returns that 'SLMgr' is not a recognized internal or external command, the cause is due to \Windows\System32 directory is not inside your environment's path. Simply type the full path of (assuming C: is Windows volume) C:\Windows\System32\slmgr, or change directory to %WinDir%\System32 before issuing the SLMgr command.

Revision #1

Created 2026-04-24 08:23:15 UTC by Nico là

Updated 2026-04-24 08:23:34 UTC by Nico là